


on the backside of the paper. On the fabric side the thread ends are trimmed leaving a tail about 1/2" long.




NOTE - Removing Papers: The foundation papers are not removed until you are ready to assemble the quilt top.

REGISTRATION LINES (TRP)

Step 1: The T-Templates have registration lines (marked as dotted lines with a TRP label). Remove each T-Template set from Bag #D2. Make sure the T-Template is stacked on top of the fabrics that are the same size and all of the edges are perfectly aligned in each set. The **T-Templates** that include TRP Lines are shown graphically below

Step 2: Unthread your machine, and replace the needle with a size 90/80. With the first T-Template Set at your machine, perfectly aligned with the fabric beneath, sew through the paper and the fabrics with just the needle, marking the registration lines on each fabric.



Step 3: Change the needle back to the 70/80 needle. Re-thread the machine and set the stitch length = 2.8 and sew on the lines marked by the needle-punching. Repeat this process with each T-Template set.

NOTE - Marking Pencil Option: Double check the needle punch holes against the T-Template before sewing each piece. If the needle punch holes do not match because the pieces weren't perfectly aligned when punched, you may need to use a marking pencil and mark the registration lines on the backside of the fabric. This can be done by cutting out a thin line on each registration line on the paper template. Replace the templates matching the backside of the template up with the wrong-side of the fabric. With a light pencil mark the fabric along each of the cut registration lines.

ASSEMBLE THE BORDER UNITS

► Illustration 1

Arrange the Foundation Units and T-Templates onto your design wall as shown. Remove all the foundation papers from the backside of each Unit. Make sure you don't get your Units or T-Templates mixed up. If you mix them up none of the (TRP) lines will match up. Before you begin to sew these units together, make sure your stitch length is set back to normal for paper-piecing and that you have set your machine to sew a 1/4" seam.

► Illustration 2

Step 1: Join Unit D1 to **T-Template D7**. The seam is pressed towards Template D7.

Step 2: Join Unit D2 to **T-Template D8**. The seam is pressed towards Template D8.

Step 3: Join Unit D3 to **T-Template D9**. The seam is pressed towards Template D10.

Step 4: Join Unit D4 to **T-Template D10**. The seam is pressed towards Template D11.

Step 5: Join Unit D5 to **T-Template D11**. The seam is pressed towards Template D9.

Step 6: Join Unit D6 to **T-Template D12**. The seam is pressed towards Template D8.

Step 7: Join **T-Template D1** to **T-Template D2**. The seam is pressed towards **T-Template D2**.

► Illustration 3

Step 8: Match and pin the (TRP) lines before you sew. Join the pieces as shown in Illustration 3 to complete Group 1 and 2.


Step 9: The Illustrations show the pressing from the front side. The diagonal seams are pressed Counter Clockwise on the back showing clockwise on the front.

► Illustration 4


Step 10: Join the (3) groups as shown to complete the Corner Units.

Step 11: The last two seams on each corner are pressed towards the center. As shown with the arrows.


► **Illustration 1**



► **Illustration 2**



► **Illustration 3**



► **Illustration 4**

