

Step 2: Clip the Sec Temp to the fabric beneath. Place in Bag #B1.



► Fabric B3: Temps B1-4 & B1-5

Step 1: Cut (8) 2" by 42" strips from *Fabric B3*. Stack the strips facing **right-side-up** on your table. Use *Temp B1-4* and *Temp B1-5* to cut (8) pieces matching the size of each template.



Step 2: Paper clip the section templates to the fabric beneath and place in Bag #B1.



► Fabric B4: Temps B1-8 & B1-9

Step 1: Cut (8) 2" by 42" strips from *Fabric B4*. Stack the strips facing **right-side-up** on your table. Use *Temp B1-8* and *Temp B1-9* to cut (8) pieces matching the size of each template.



Step 2: Paper clip the section templates to the fabric beneath and place in Bag #B1.



► Fabric B5: Temps B1-12 & B1-13

Step 1: Cut (4) 2" by 42" strips from *Fabric B5*. Stack the strips facing **right-side-up** on your table. Use *Temp B1-12* and *Temp B1-13* to cut (8) pieces matching the size of each template.




Step 2: Paper clip the section templates to the fabric beneath and place in Bag #B1.



► Fabric B6: (TLS) #3

Step 1: Cut (2) 4-1/2" by 42" strips from *Fabric B6*. Position each strip facing **right-side-up** on your table. **DO NOT STACK!**

Step 2: Position (2) of *Unit B1 (TLS) #3* onto each strip. The backside of each layout sheet is placed against the right-side of the fabric and secured with repositionable glue.



Step 3: Cut along the edge of each layout sheet, leaving about 1/4" of excess fabric along each edge. Set your stitch length on your machine to sew a basting stitch [see (TRP) section on page 5 under General Piecing Instructions] and sew on the (TRP) lines on each layout sheet.

NOTE - Important: (TRP) lines are needed when curved piecing, so don't skip this step!




Then trim fabric even with (TLS).

Step 4: After the (TRP) lines are sewn, trim off the threads left dangling from your (TRP) Lines on the front and backside of each

layout sheet. Trim the excess fabric off around the perimeter, then cut the individual template sections apart each on Cut Line in numerical order. Cut Lines 2 & 3 are the sew sides for your curved seams. Do not skip these lines.


Step 5: Discard the scraps after cutting on Cut Line 3. Leave the template attached to fabric until you are ready to complete the curved paper piecing. Place the (8) Temp B1-16 pieces in Bag #B1.



► Fabric B7: (TLS) #4

Step 1: Cut (1) 5-3/4" by 42" strip from *Fabric B7* and place **right-side-up** on your table.

Step 2: Position (4) of *Unit B1 (TLS) #4* onto the strip. The backside of each layout sheet is placed against the right-side of the fabric and secured with repositionable glue.



Step 3: Cut along the edge of each layout sheet, leaving about 1/4" of excess fabric along each side. Set your stitch length on your machine to sew a basting stitch [see (TRP) section on page 5 under General Piecing Instructions] and sew on the (TRP) lines on each layout sheet.



Step 4: After the (TRP) lines are sewn, trim off the threads left dangling from your (TRP) Lines on the front and backside of each layout sheet. Trim the excess fabric off around the perimeter, then cut the individual template sections apart on each Cut Line in numerical order. Cut Lines 2 & 3 are the sew sides for your curved seams. Do not skip these lines.



Step 5: Discard the scraps left over after cutting on Cut Lines 2 & 3. Leave the template paper attached to each fabric piece until you are ready to complete the curved paper piecing. Place these in Bag #B1.



STACKING: UNIT B1, SEC. 1-15, BAG #B1

Position the templates and fabric pieces B1-1 through B1-15 for Unit B1 in numerical order facing **right-side-up** with the **sew-sides** aligned at the top. Sec. 1 does not have a sew side.

