


Adding Sec Fabric #2

Step 6: Position the fabric piece for Sec. 2, *right-side up* next to the folded back paper.

Step 7: Lift the foundation paper and slide the fabric under Sec. 2. Make sure it aligns with the trimmed seam allowance and extends beyond the dashed boundary lines for Section 2.

Step 8: Open the paper and sew on Line 1, starting and stopping 1/8" beyond the sew line. Complete the sewing on each unit 1-8.

Step 9: Loosen the glue under Sec. 1. Fold the fabric over to cover Section 2, on the foundation paper and press. Before moving onto the next step verify the fabric overlaps the Section 2 boundary on the backside of the paper.




Repeating Graphics and Instructions for the Remaining Sections

Step 10: a.) Place the fold template over the top of Sec. 1 aligning it with 2. b.) Fold the paper back, then tear the paper along the stitches on Line 1 about 1/2", stop when you hit the fold template.


NOTE - Tearing the paper along the stitches separates the fabric from the paper. This allows the fabric to lay flat against the table, making it easier to align the Add-A-Quarter ruler along the folded edge.

Step 11: a.) Trim the fabric with the *Add-A-Quarter* ruler. b.) Position the fabric piece for Sec 3 *right-side-up* and slide it under Sec. 3, aligning it with the trimmed seam allowance. c.) Open the paper, sew on Line 2. Press the fabric on the backside of the paper.



Step 12: Continue adding the fabric pieces to each section, stopping once you complete Sec 9.

Step 13: After completing Section 9, adjust your stitch length to 2.2 and sew Basting Line 9, along with the- (TRP) Lines indicated with the arrows. Trim the thread ends on both sides of each unit. Do not trim the foundation papers.



CURVED PAPER PIECING

Preparation:

NOTE - Ensure the TRP lines have been sewn on templates B5-10 and B6-10.

Aligning and Gluing Template B5-10

Step 14: Position *Unit B5, fabric-side-up* on your table. Place *Temp B5-10* facing *wrong-side-up* on top of *Unit B5*.

Step 15: Match and pin the TRP Lines, then glue the raw edges of *Temp B5-10* along the basting stitch line to secure.


Curved Sewing (Sew Line 10)

Sew directly on Sew Line 10 with the paper facing up and fabric on the bottom. To prevent puckers, lift the paper about 1/2" above the machine surface as you sew. This allows the fabric to move smoothly over the feed dogs.

Step 16: After sewing, press the fabric on the back of the paper to cover Section 2.

Trimming:

Step 17: Trim the excess fabric along the curved edges around the perimeter of the foundation unit, following the printed seam allowance line.




Step 18: Once the paper is trimmed, place the unit fabric-side-up and fold back the Section 10 fabric. Trim the excess paper and fabric under Sec 10, along the basting stitches to create a clean scant 1/4" seam allowance. For detailed illustrations and instructions on trimming, refer to the Introduction Booklet.

Step 19: The vein is repressed to complete the process.

UNIT B6

Repeating Process for Unit B6:

The strips you've completed for Units B5-(including stacking, paper piecing, and curved paper piecing)- will be repeated for Unit B6. Follow the same process and techniques as outlined earlier to prepare and assemble the Unit 'B6 foundation pieces.



Color Option 2: Curved Paper Piecing Graphics

The curved paper piecing for section 10 on Units B5 and B6 are exactly the same process as outlined above for the Standard Option. The only difference is, you replaced sections 1-9 with a single piece of fabric.