

Frame It Up! Border

Quiltworx.com
Judy Niemeyer Quilting

JNQ00292B001 Adjustable Panel Border

68" x 48", 54", or 60"

GROUP B: BORDER INSTRUCTIONS

Introduction: These instructions provide everything you need to complete the Frame It Up! border shown on the cover quilt, including foundation papers, templates, cutting instructions, and assembly layouts. The border is designed to fit one of three **Panel Sizes**—[44" x 24"] [44" x 30"] or [44" x 36"]—making it compatible with a variety of panels produced in varying sizes and designed by different fabric companies. Before beginning, you may want to reference the Assembly Layouts on **Pages 15 to 19 of this booklet and 6 to 9 of the Introduction Booklet**, to understand how to size your panel and add the borders.

Preparing the Foundation Papers: This package includes enough foundation papers to complete one of the three adjustable border options. The foundation papers and templates are printed on newsprint which is lightweight and tears away from your stitches without damaging the threads. Before beginning, separate the contents of this package and verify that all newsprint pages listed below are included.

- (2) NP 1178
- (2) NP 1179
- (2) NP 1180
- (1) NP 1181
- (1) TP 1016
- (1) TP 1017
- (1) TP 1018
- (1) TP 1019





Ziploc Storage Bags: You will need (7) large Ziploc bags to complete the organization for these instructions. Label large bags as follows to stay organized as you work through the cutting process and the Foundation Paper Piecing for the individual units.

- **Bag #B1:** (2) Units B1, B2, B4, and B5, and (10) Unit B3
- **Bag #B2:** (2) Units B6, B7, B9, and B10, and (10) Unit B8
- **Bag #B3:** (2) Units B11, B12, and Alts 1-3-B14, and (8) Unit B13
- **Bag #B4:** (2) Units B15, B16, and Alts 1-3-B18, and (8) Unit B17
- **Bag #B5:** (2) Units B19, B20, B21, and B22
- **Bag #B6:** (4) Unit B23, B24, and B25

Template Bag #B7: Place all Templates and TLS on Newsprint NP 1180, NP 1181, and all of the TP sheets into this bag, in alphanumeric order. These will stay here until you are ready to begin cutting, then the pieces will be sorted into the proper bags when the cutting is complete.

Cutting and Sorting Your Newsprint: Cut out the foundation units, Templates, T-Templates, and TLS printed on [NP 1178 to 1181, and TP 1016 to 1019]. Then, place into their assigned bags as listed above. On NP 1179 and 1181, there are Alternative blocks for Units B14 and B18. Cut out only the Unit Alternative for the size panel you are adding the border to. Also, on TP 1018 and 1019, there are **Alt T-Temps B-1 to B4**. You may or may not choose to use these. See Pages 2 and 3 to determine which version of this panel border you want to make. Reference the **newsprint graphics** that follow for the location of each Unit, Template and (TLS) on each sheet. Reference the ziploc bags section above, for where to put everything. *For additional guidance, refer to the General Information section for Foundation Papers and Templates for instructions on proper preparation. This information is in your Introduction Booklet.

After the cutting is complete, place the fabric pieces, Sec. Temp's, T-Temp's, and (TLS) into the bags along with the corresponding foundation papers as outlined in the cutting instructions.



► **Fabric A2, 1" Sashing (See Pages 6 to 9 of the intro booklet before cutting. You may want a different width):**

Cutting for your sashing strips depends on the size panel you have selected and the size sashing strip you would like to have. Please reference the Introduction Booklet for more information.

■ **CUTTING FOR THE 24", 30", AND 36" SHORT EDGE**

The Yardage table on the following page includes information on the fabric references and the yardage for each of the three sizes of the short edge.

■ **CUTTING SHORT EDGE**

► **Fabric BS1 (24" Panel)**


Templates Used:

- **TLS #7 & #8, (2) Temp B-11**

Step 1: Cut (1) 4-1/2" x 42" strip from *Fabric BS1*. The strip is placed on your table, facing *right-side up*.

(1) 4-1/2" x 42" Strips


Step 2: TLS #7 and #8 have a line on them that says Trim Line for 24" Panel. Cut the TLS apart on this Trim Line. (TLS #8 is shown as an example to the right.)




Step 3: Place the trimmed *TLS #7*, *TLS #8*, and (2) *Temp B-11* onto the 4-1/2" strip as shown below. Trim around the TLS and Templates cutting (2) pieces the size of *TLS #7 and #8*, and (4) pieces the size of *Temp B-11*. Reposition the Templates and TLS to cut the second set.



Step 4: Clip (2) *Temp B-11* together with (1) *Temp B-11* template on top of each stack. Place (1) into Bag #B3 and (1) into Bag #B4.



Step 5: Restack the fabrics cut with TLS #7 and #8, then place the template on top. Cut the TLS and fabrics beneath apart on the cut lines, clip the stacks together, and place the TLS #7 pieces into Bag #B3 and the TLS #8 pieces into Bag #B4.



► **Fabric BS1 (30" and 36" Panel)**

Templates Used:


- **TLS #7 & #8, (2) Temp B-11**

Short Side Yardage Chart, Make 2				
GROUP-B FABRIC #	24" YDS INCH	30" YDS INCH	36" YDS INCH	ASSIGNED COLOR
Fabric BS1 TLS #7 & #8, Temp B-11	1/8 Yd, or 4-1/2"	1/4 Yd, or 9"	1/4 Yd, or 9"	Fabric Swatch
Fabric BS2 TLS #5, #9, #10, #11, #12	3/8 Yd, or 13-1/2"	1/2 Yd, or 17"	1/2 Yd, or 17"	Fabric Swatch
Fabric BS3 TLS #6	1/8 Yd, or 3-1/2"	1/8 Yd, or 3-1/2"	1/4 Yd, or 7"	Fabric Swatch
Fabric BS4 TLS #6	1/8 Yd, or 3-1/2"	1/8 Yd, or 3-1/2"	1/4 Yd, or 7"	Fabric Swatch
Fabric BS1 Alt Alt T-Temp B-1 to B-4	3/8 Yd, or 13-1/2"	3/8 Yd, or 13-1/2"	3/4 Yd, or 27"	Fabric Swatch
Fabric BS5 Temps B-15, B23-3, B25-2	1/8 Yd, or 4"	1/8 Yd, or 4"	1/8 Yd, or 4"	Fabric Swatch
Fabric BS6 Temps B-20, B23-1, B24-2, B25-4	1/8 Yd, or 4-1/2"	1/8 Yd, or 4-1/2"	1/8 Yd, or 4-1/2"	Fabric Swatch
Fabric BS7 Temps B25-3, B24-3, B24-5, B25-5, Temps B-19, B-21, B-23, B-24	1/2 Yd, or 18"	1/2 Yd, or 18"	3/4 Yd, or 25"	Fabric Swatch
Fabric BS8 Temps B-25, B-24-6 & B-25-6	1/4 Yd, or 7-1/2"	1/4 Yd, or 7-1/2"	3/8 Yd, or 10"	Fabric Swatch


Step 1: Cut (2) 4-1/2" x 42" strips from *Fabric BS1*. The strips are placed on your table, facing *right-side up*.

(2) 4-1/2" x 42" Strips


Step 2: Place *TLS #7*, *TLS #8*, and (2) *Temp B-11* onto the 4-1/2" strip as shown below. Trim around the TLS and Templates cutting (2) pieces the size of *TLS #7 and #8*, and (4) pieces the size of *Temp B-11*. Reposition the Templates and TLS to cut the second set.



Step 3: Clip (2) *Temp B-11* together with (1) *Temp B-11* template on top of each stack. Place (1) into Bag #B3 and (1) into Bag #B4.



Step 4: Restack the fabrics cut with TLS #7 and #8, then place the template on top. Cut the TLS and fabrics beneath apart on the cut lines, clip the stacks together, and place the TLS #7 pieces into Bag #B3 and the TLS #8 pieces into Bag #B4.



For the 30" Panel, discard one of the Sec. 4, Temp B-9 and Sec. 4 Temp B-7